


Crop Water Use by Growth Stage – Soybeans

Soybean Growth Stages

- VC: Cotyledon leaves with unifoliate leaves unrolled.
- V1: 1st node containing trifoliolate leaf fully expanded.
- V2: 2nd node containing trifoliolate leaf fully expanded.
- V3: 3rd node containing trifoliolate leaf fully expanded.
- R1: At least one flower on any node.
- R3: A pod 3/16 inch on one of four uppermost nodes.
- R5: Seed is 1/8 inch long in a pod of the upper four nodes.
- Begin Maturity: one brown leaf on main stem.



Weekly ET_{gage}® Change in Inches

Crop Stage	Kc	1.00	1.10	1.20	1.30	1.40	1.50	1.60	1.70	1.80	1.90	2.00	2.10	2.20	2.30	2.40	2.50	2.60	2.70	2.80	2.90	3.00
VC Cotyledon	0.10	0.10	0.11	0.12	0.13	0.14	0.15	0.16	0.17	0.18	0.19	0.20	0.21	0.22	0.23	0.24	0.25	0.26	0.27	0.28	0.29	0.30
V1 1st Node	0.20	0.20	0.22	0.24	0.26	0.28	0.30	0.32	0.34	0.36	0.38	0.40	0.42	0.44	0.46	0.48	0.50	0.52	0.54	0.56	0.58	0.60
V2 2nd Node	0.40	0.40	0.44	0.48	0.52	0.56	0.60	0.64	0.68	0.72	0.76	0.80	0.84	0.88	0.92	0.96	1.00	1.04	1.08	1.12	1.16	1.20
V3 3rd Node	0.60	0.60	0.66	0.72	0.78	0.84	0.90	0.96	1.02	1.08	1.14	1.20	1.26	1.32	1.38	1.44	1.50	1.56	1.62	1.68	1.74	1.80
R1 Begin Bloom	0.90	0.90	0.99	1.08	1.17	1.26	1.35	1.44	1.53	1.62	1.71	1.80	1.89	1.98	2.07	2.16	2.25	2.34	2.43	2.52	2.61	2.70
R2 Full Bloom	1.00	1.00	1.10	1.20	1.30	1.40	1.50	1.60	1.70	1.80	1.90	2.00	2.10	2.20	2.30	2.40	2.50	2.60	2.70	2.80	2.90	3.00
Begin Pod Full Pod R5 Begin Seed Full Seed	1.10	1.10	1.21	1.32	1.43	1.54	1.65	1.76	1.87	1.98	2.09	2.20	2.31	2.42	2.53	2.64	2.75	2.86	2.97	3.08	3.19	3.30
Begin Mature	0.90	0.90	0.99	1.08	1.17	1.26	1.35	1.44	1.53	1.62	1.71	1.80	1.89	1.98	2.07	2.16	2.25	2.34	2.43	2.52	2.61	2.70
Full Mature	0.20	0.20	0.22	0.24	0.26	0.28	0.30	0.32	0.34	0.36	0.38	0.40	0.42	0.44	0.46	0.48	0.50	0.52	0.54	0.56	0.58	0.60
Mature	0.10	0.10	0.11	0.12	0.13	0.14	0.15	0.16	0.17	0.18	0.19	0.20	0.21	0.22	0.23	0.24	0.25	0.26	0.27	0.28	0.29	0.30

This chart can be used with readings from an ET_{gage}® or other ET reference. First, identify the change in the ET rate across the horizontal row and then identify the current growth stage in the left column. Follow the two columns to the point where they intersect to identify the ET rate to use in your irrigation scheduling. When planning irrigation, account for soil moisture, precipitation, weather conditions, and the ET rate for growth stage of your crop.